

## Small Grain - Oats (Code #012)

Soil Test Rating	Potassium			
	Low K	Medium K	High K	Very High K
	Coast: 0-60 lbs/A Pied: 0-100 lbs/A	Coast: 61-150 lbs/A Pied: 101-200 lbs/A	Coast: 151-250 lbs/A Pied: 201-350 lbs/A	Coast: 250+ lbs/A Pied: 350+ lbs/A
Phosphorus	<i>Recommended Pounds N-P<sub>2</sub>O<sub>5</sub>-K<sub>2</sub>O per Acre</i>			
<b>Low P</b>  Coast: 0-30 lbs/A Pied: 0-20 lbs/A	*-80-80	*-80-40	*-80-0	*-80-0
<b>Medium P</b>  Coast: 31-60 lbs/A Pied: 21-40 lbs/A	*-40-80	*-40-40	*-40-0	*-40-0
<b>High P</b>  Coast: 61-100 lbs/A Pied: 41-75 lbs/A	*-0-80	*-0-40	*-0-0	*-0-0
<b>Very High P</b>  Coast: 100+ lbs/A Pied: 75+ lbs/A	*-0-80	*-0-40	*-0-0	*-0-0

Coast = Coastal Plain    Pied = Piedmont, Mountain, and Limestone Valley

### Recommendations:

Recommended pH:	6.0. If the pH is less than 6.0, see Lime Table C.								
Nitrogen:	60-100 pounds nitrogen (N) per acre								
Magnesium:	If soil test Mg level is low and lime is recommended, use dolomitic limestone; if soil test Mg is low and lime is not recommended, apply 25 pounds of Mg/Acre.  <table border="1" style="margin-left: auto; margin-right: auto;"> <tr> <td>Coastal Plain</td> <td>Low: 0 - 30 lbs/acre</td> <td>Medium: 31 - 60 lbs/acre</td> <td>High: &gt;60 lbs/acre</td> </tr> <tr> <td>Piedmont</td> <td>Low: 0 - 60 lbs/acre</td> <td>Medium: 61 - 120 lbs/acre</td> <td>High: &gt;120 lbs/acre</td> </tr> </table>	Coastal Plain	Low: 0 - 30 lbs/acre	Medium: 31 - 60 lbs/acre	High: >60 lbs/acre	Piedmont	Low: 0 - 60 lbs/acre	Medium: 61 - 120 lbs/acre	High: >120 lbs/acre
Coastal Plain	Low: 0 - 30 lbs/acre	Medium: 31 - 60 lbs/acre	High: >60 lbs/acre						
Piedmont	Low: 0 - 60 lbs/acre	Medium: 61 - 120 lbs/acre	High: >120 lbs/acre						
Other:	See sulfur (S) recommendations below.								

### Fact Sheet:

For oats following a legume apply 60 pounds nitrogen per acre; for oats following cotton, corn, etc. apply 80 pounds nitrogen per acre; for oats following grain sorghum apply 100 pounds nitrogen per acre. Apply 20 to 40 pounds of the recommended nitrogen per acre in the fall and the remainder in February.

#### Coastal Plain only:


On deep sandy soils, apply 10 pounds of sulfur (S) per acre. The sulfur should be applied when the topdress nitrogen application is made.

### Small Grain - Oats (Code 012)

VEI - I


P Recommendations, Coastal Plain

$$P_2O_5 = 102 - 1.509P + 0.00293P^2$$




K Recommendations, Coastal Plain

$$K_2O = 98 - 0.622K + 0.00066K^2$$



P Recommendations, Piedmont

$$P_2O_5 = 103 - 2.459P + 0.01148P^2$$



K Recommendations, Piedmont

$$K_2O = 103 - 0.472K + 0.00036K^2$$

